

The Vital Link between Land and Water: The Importance of Uplands for Protecting Wetland Functions ¹

Amy K. Taylor, Patricia Sprott, and Frank J. Mazzotti²

Overview

Wetlands are valuable natural resources that provide many benefits to people and the environment. Their importance can be described in terms of the functions they perform, including flood control, water quality enhancement, water supply, wildlife habitat, energy transfer (from plant to animal or from animal to animal, as in the food chain), and nutrient cycling (movement of chemicals--such as nitrogen or carbon or oxygen--through the system), as well as contributing much to Florida's natural beauty. The occurrence of both wetlands and uplands is dependent upon the local geography, topography, geology, hydrology, soil types, and frequency of fire. A wetland occurs in a low spot in the topography and is defined by and dependent upon the surrounding upland habitats. In recognition of their environmental and economic value, wetlands are legally protected at the local, regional, state, and national level. Unfortunately, the upland habitats bordering freshwater wetlands have not been provided protection to the same extent as wetlands.

Upland Habitats

Upland habitats have been extensively developed for residential and agricultural use, often right up to the wetland boundaries. Such development may well result in degradation and loss of the value for which wetlands were protected. The wetland functions most threatened by loss of upland habitats are water quantity and quality, energy and nutrient systems, and wildlife habitat.

Upland Surface Water Dependency

The relationship between surface water in wetlands and ground water in the surrounding uplands is complex, but frequently in Florida, the wetland's surface water is dependent upon the upland's ground water. Drilling wells in an upland to supply water for development or agriculture will reduce the ground water level and decrease the depth of water and the hydroperiod (the length of time the surface is inundated) in the nearby wetland. This decrease can cause changes in the structure and composition of the wetland community. The usual result following drainage of a wetland is a

-
1. This document is WEC45, one of a series of the Wildlife Ecology and Conservation Department, Florida Cooperative Extension Service, Institute of Food and Agricultural Sciences, University of Florida. Original publication date December, 1990. Revised September, 2002. Reviewed and renumbered May, 1999 as SS-WIS-45. Visit the EDIS Web Site at <http://edis.ifas.ufl.edu>.
 2. Amy K. Taylor, wildlife intern, Patricia Sprott, wildlife information specialist, and Frank J. Mazzotti, Ph.D., associate professor, Wildlife Ecology and Conservation department, University of Florida, Everglades REC, Belle Glade, FL 33430, Florida Cooperative Extension Service, Institute of Food and Agricultural Sciences, University of Florida, Gainesville, 32611.

The Institute of Food and Agricultural Sciences (IFAS) is an Equal Employment Opportunity - Affirmative Action Employer authorized to provide research, educational information and other services only to individuals and institutions that function without regard to race, creed, color, religion, age, disability, sex, sexual orientation, marital status, national origin, political opinions or affiliations. For information on obtaining other extension publications, contact your county Cooperative Extension Service office. Florida Cooperative Extension Service / Institute of Food and Agricultural Sciences / University of Florida / Larry R. Arrington, Interim Dean

replacement of the plant and animal life adapted for deeper water and a longer hydroperiod with those species adapted for shallower water and/or shorter hydroperiods. Small wetlands are the most vulnerable to changes in water levels and small wetlands with short hydroperiods can easily be completely eliminated.

Uplands and Water Quality

Uplands that border wetlands can filter, catch and retain dissolved and suspended matter carried by surface runoff of water from surrounding landscapes. When an upland adjacent to a wetland is developed, sedimentation (the increase of deposited particulate matter), can become a major water quality problem for the wetland. The upland vegetation is particularly effective at controlling sedimentation and turbidity (particulate matter suspended in water). Without the benefit of this first stage of filtration and catchment, sediments carried by overland flow can fill the wetland, eventually causing a transition to upland habitat.

Preserving Wetland and Upland Linkages

When wetlands are degraded or lost in this manner, open waters are affected, which may ultimately affect the quality of the water that recharges the aquifer. Preserving wetland and upland linkages is important to maintaining good water quality in the wetland and in the groundwater.

The major structural components of an ecosystem, including energy, chemicals and organisms, are connected by the systems of energy flow and nutrient recycling. Energy flows from the sun to primary producers (plants), through consumers (mostly animals) and finally to decomposers (bacteria and fungi), which then recycle it into the environment as essential nutrients (nitrogen, carbon, etc.). Alterations disrupting the flow of energy and nutrients between uplands and wetlands decrease the ability of each habitat to function normally.

Interactions Between Wetlands and Uplands

Interactions between wetland and upland habitats can be a major factor in determining the amount of

energy and nutrients in these systems and how the energy and nutrients are used. Wetlands provide habitat for many species of birds, mammals, reptiles, fish, amphibians, and a variety of invertebrates. These species feed and/or breed in wetlands, then spend time in adjacent upland habitats where they defecate, die, and become food for upland animals, adding both energy and organic matter to the upland community. Surface runoff then carries the organic and mineral material back into wetlands. This exchange between terrestrial and aquatic habitats provides important nutrients for both systems.

Wetland areas provide habitat for many wildlife species. Some are completely aquatic (fish). Some are semiaquatic (alligators, amphibians, and some turtles). Wetlands also provide critical habitat components for species generally considered strictly terrestrial. A typical direct upland and wetland linkage occurs when a species resides and feeds in one of these two habitats and breeds in the other. Examples: aquatic turtles [snapping turtles (*Chelydra serpentina*)], reside in wetlands and open water areas, but require adjacent uplands for nesting; and tree frogs, have the opposite pattern.

Together, amphibians and fresh water turtles often make up the majority of the biomass of the larger vertebrates in their respective habitats, and therefore can have a great effect on community structure and function. Turtles carry seeds and parasites between habitats. Amphibians often are top predators in aquatic systems and the most important prey in some terrestrial systems. The disruption or elimination of one habitat destroys the linkages that provide essential elements for species survival and could have drastic effects.

Creation of Scientifically Valid Buffer Zones?

The preservation of the linkages between uplands and wetlands is essential for protecting the structure and function of wetland systems. One solution for preserving these linkages is the creation of buffer zones to separate developed upland areas from wetland systems. But the buffer zone's size must be determined scientifically. Creation of upland buffer zones is controversial because it changes the designation of land previously considered suitable for

development. This carries a considerable economic cost and must, therefore, be strongly justified.

Although buffer zones can protect some of the aquatic and terrestrial linkages, they will not protect them all. For example, the importance of the amphibian component of a wetland contribution to local energy cycles extend far beyond their borders. Some frogs and toads utilize habitat surrounding their breeding ponds up to a distance of 2km (1.24mi). A buffer of 2km around a small pond to protect this food web interaction would encompass 1300ha (3211ac). Since small wetlands tend to be scattered widely over the landscape, an upland of this size set aside to completely protect this linkage would not be realistic in a development site plan, but might be in a large, intact area such as a mitigation bank.

As we learn more about wetland functions we realize the challenges in preserving them. Our ability to predict the effects of upland habitat loss on wetland habitats must be improved to provide a scientific basis for sound natural resource management decisions. Only then can these decisions reduce or eliminate negative impacts caused by urban growth.

References

Moler, P.E. and R. Franz. 1987. "Wildlife values of small isolated wetlands in the southeastern coastal plain." Pp. 234-238. In: *Proc. of the Third SE Nongame and Endangered Wildlife Sym* . Ga. Dept. Nat. Res.